



Critical
manufacturing
an ASM PT company

Experiment Management

10.2

March 2024

DOCUMENT ACCESS

Public

DISCLAIMER

The contents of this document are under copyright of Critical Manufacturing S.A. it is released on condition that it shall not be copied in whole, in part or otherwise reproduced (whether by photographic, or any other method) and the contents therefore shall not be divulged to any person other than that of the addressee (save to other authorized offices of his organization having need to know such contents, for the purpose for which disclosure is made) without prior written consent of submitting company.

Experiment Management

Estimated time to read: 26 minutes

With the Experiment Management module you can overcome the challenges of combining experiment lots with production lots by ensuring that experiments run in a smooth and transparent way for users and the applications that support manufacturing operations.

The Experiment Management module is fully integrated with the MES to support the design of the experiment (DoE) and the execution of the experiment. Experiment lots are tracked and processed in the same way as any other lot and the system automatically enforces the set variations.

Using the Experiment Management module of Critical Manufacturing MES leads a faster speed of learning, increased visibility, tracking and monitoring of experiments, increased operational efficiency, and the reduction of errors.

Info

Experiment Management is a separately licensed module.

This document will guide you through the setup and usage of Experiment Management functionalities.

Overview

The Experiment Management module allows you to define and carry out controlled experiments on the shop-floor. An Experiment consists of well-defined variations, such as a different Recipe or different BOM, for which you want to test the effect of that variation, typically against a control group, typically assigned to the POR (**Process of Record**). When using sub-materials (an Experiment Definition mode designated as **Sub-Materials**), it is possible to assign sub-materials to Material Groups, and then define specific variations at different process Steps for those Material Groups. Because multiple Material Groups are supported, it is possible to carry out several Experiments in a single Material. When no sub-materials are available all variations will be applied to the complete material - this Experiment Definition mode is called **Full Material**. The execution of the Experiment is enforced by the system and it is transparent for the operator.

Concepts


The main concepts related with the Experiment Management module are described in the table below:

Term / Concept	Description
Experiment Definition	A structured definition of the specific variations to be applied to a Material or to specific Material Groups during an Experiment.
Experiment	The running Experiment based on an Experiment Definition. An Experiment always require a Material.
Objective	A goal to be tested by the Experiment Definition, such as cost, yield or performance.
Material Group	A group of Sub-Materials that will be subject to some variations together.

Term / Concept	Description
Step Material Groups	The Steps where Material Groups will be subject to for specific process deviations.
Action	A deviation to be applied for a Material or a Material Group at an Experiment Definition Step.
Event	The trigger for an Action.


Table: Experiment Management main concepts

The Experiment Management object model is shown below:




Experiment Management Lifecycle

There are essentially two core objects that make up the Experiment Management Module as shown in the image below. The Experiment Definition (shown in blue) is a template from which Experiments can be created. The Experiment (shown in green) is the actual running Experiment and that must have a Material associated with it. The Experiment Definition is a versioned object that follows the normal lifecycle of a versioned object.



The Experiment object that represents the running Experiment Definition instance and that always requires a Material follows the lifecycle as shown in the image below and described in the table immediately after:



State	Description
Created	This is the default state when an Experiment is created by assigning a Material to it. There are several restrictions regarding which Materials can be assigned to a particular Experiment Definition such as the Product, the Flow, the Type, the Form as well as the number and form of the Sub-Materials.
InProgress	When the Material reaches the first Step defined in the Experiment Definition it becomes InProgress.
Completed	When the Material is moved out of the last Experiment Definition Step, it becomes Completed.
Closed	When the user marks the Experiment as closed, the Experiment is closed. Typically, the Experiment results are recorded before the Experiment is closed.

Table: Experiment object lifecycle

Info


An Experiment Definition can be configured to automatically close the Experiment automatically after the last Experiment Step.

During execution there are four important events that the Experiment Management module considers to carry out actions. These are described in the table below:

Event	Description
Queued	Triggered when the Material or Material Group arrives at the Step.
Track-In	Triggered when the Material is being Tracked-In.
Track-Out	Triggered when the Material is being Tracked-Out.
Processed	Triggered after the Material has been Tracked-Out (but not yet moved to the next Step).

Table: Experiment management events

Any Experiment Definition Action must always be associated with one of the four events. The execution of the Experiment by the system is shown in the image below:



Some actions require that a split takes place before the action is performed. All splits are defined per Experiment Definition Step Material Group and will be evaluated and performed when the Material arrives at the Experiment Definition Step.

Note

At every Experiment Definition Step, there must be one Material Group that is not Split, that is, its Split Type must be **None**.

Split Type	Description
None	No split is performed.

Split Type	Description
Logical	<p>The Material Group is logically split in the system automatically, even though physically it will remain together. There are three types of physical splits:</p> <ul style="list-style-type: none"> - For Current Step - a temporary split where the Material Group is merged back at the end of the current Step (in state Processed). - For Multiple Steps - a temporary split where the Material Group is merged back at another Step further ahead in the Flow. In this case, it is necessary to provide a merge point, that is, the merge Flow Path. And also the merge state. - Permanent - in this case, the Material Group is split permanently and will not be merged back again.
Physical	<p>The Material Group is split logically and physically. There are three types of physical splits:</p> <ul style="list-style-type: none"> - For Current Step - a temporary split where the Material Group is merged back at the end of the current Step (in state Processed). - For Multiple Steps - a temporary split where the Material Group is merged back at another Step further ahead in the Flow. In this case, it is necessary to provide a merge point, that is, the merge Flow Path. And also the merge state. - Permanent - in this case, the Material Group is split permanently and will not be merged back again.

Table: Experiment Material Group split types

Setting Up an Experiment Definition

Create the Experiment Definition

An Experiment Definition can be created as any versioned object in the system. The next sub-sections will cover the Experiment Definition creation steps in more detail.

General Data

The table that follows describes properties that need to be taken into account when creating an Experiment Definition as part of the first step of the Experiment Definition creation wizard as shown in the image below.

Field	Description
Owner Role	If defined, it restricts the modifications of this Experiment Definition to this role.
Applicable To	To restrict the material to be selected on an Experiment, there are two options available: Product or Product Group. Depending on the selection, it will only be possible to select a material which fits the option. Neither of the two are mandatory and only the Flow can be defined
Flow	The Flow in which the Experiment will be executed. If Product or Product Group is not defined any material running in this flow (And that matches the other conditions below) can be selected for the Experiment. If the selected product has a default Flow, it will be automatically filled out.


Field	Description
Maximum Number of Materials	The maximum number of materials which can be used in an Experiment.
Mode	<p>The Mode selected determines if the Experiment uses Sub-materials or Full Material. If the selected mode is Full Material, only Materials without Sub-Materials can be used; if the selected mode is Sub-Materials, the field Required Sub-Materials Count must be greater than zero.</p> <p> If zero is indicated, the experiment will be carried out in the entire material.</p> <p>Required Sub-Materials Form can also be indicated.</p>
Ignore Sampling Plans	This option determines if during the execution of the Experiment, Sampling Plans are ignored.
Ignore <u>SPC</u> Charts	This option determines if during the execution of the Experiment, the DataCollection Parameters values from the Experiment action "SetDataCollection" are ignored and not send to the <u>SPC</u> Chart.
Close Experiment Automatically	This option determines if, when completed the last step of the experiment, it will be closed automatically. After completed, it will still be shown in the experiment's list.

Table: General Data tab steps

[illegible]


Objectives

The Objectives wizard step, is used to capture the objectives of the Experiment as shown in the table and image below:

Field	Description
-------	-------------

Field	Description
Name	Each objective's name must be unique. However, it can be re-used across different Experiment Definitions. The available objectives must be listed in the Lookup table ExperimentDefinitionObjective .
Description	An optional field, only used for informative purposes.
Target	An optional field, only used for informative purposes.

Table: Objectives tab steps



Material Groups

The definition of the Material Groups is necessary if the selected **Mode** in the **General Data** tab is **Sub-Materials**. These groups are used to assign variations (actions) during the course of the Experiment.


Note

These are the primary (main) groups and it is possible to define other groups for a particular Experiment Definition Step.


The first image below displays the Material Groups definition page. Besides this view, a matrix view is also available, as shown in the image below. The matrix view is accessed by selecting the corresponding icon on the top right-hand corner of the screen. The matrix view provides a general overview of the assignment and enables the association and disassociation of a material number to a group, by selecting the corresponding area.

- Each Material Group can define a Material Type. If set, all Sub-Materials assigned to this group will be changed to this material type automatically when the Experiment is created.
- For information purposes, each Material Group can be marked as **shippable** or not to indicate whether a certain Material Group can be shipped. Remember that this option is for information only and doesn't have any functional effect, meaning that the material can still be shipped.

- There are as many Sub-Materials available to assign to material groups as the value defined in **Required Sub-Materials Count**.
- Each Sub-Material number must be associated with one and only one Material Group.
- The mapping between the sub-material slot ID and sub-material is performed when it is first assigned to the Experiment.
- Select the mandatory Sub-Materials and optional Sub-Materials. If any Sub-Material is left unselected for any Material Group, a visual indication will be displayed below the Material Groups panel.




When viewing the Material Groups as a matrix, you can choose a specific Sub-Material as mandatory or optional by selecting the proper option on the top right of the matrix and picking the right cell on the matrix.



Material Groups	1	2	3	4	5	6	7	8	9	10
Process 1	1*	2*	3*	4*						
Process 2						6*	7*		9	10

Define Experiment Definition Steps and Actions

After creating the basic Experiment Definition object, you then need to define the actions to be performed at each Step for each Material Group. This can be defined in the Experiment Definition Matrix view, by selecting the option **Add Step**, as shown in the image below:



General Data

In this tab you must select the Flow Path for which it is intended to perform an action on a Material Group. **And if MaterialGroup Mode = Sub-Material**, define how different Material Groups are defined for entering and leaving the Step. The available options are: - Enter - Material Groups are defined when entering the Step. - Enter and Exit - Material Groups can be defined on entering and leaving the Step. As shown in the image below:

+ Add Experiment Definition Step

① GENERAL DATA — ② MATERIAL GROUPS — ③ ACTIONS

General Data

* Flow and Step:

MOSRM8H[A]

Ash Clean

Browse

Flow Path: MOSRM8H [A] > Ash Clean

Material Groups Mode:

Enter

Enter and Exit

Exit Step Split and Merge Type:

Logical

Physical

Ignore in Sampling Plans:

Ignore in SPC Charts:

Comments:

Cancel

< Back

Next >

i Info

If option **Enter and Exit** is selected: - At Enter: SplitType must be permanent in order to create new Material Group at Exit. - At Exit: Only Actions Hold, Change Flow And Step, Temporary Off Flow, Terminate And Send Mail can be selected because only these actions can be set once the material is processed

Info

The Flow Paths selected can be different from the one defined in the Experiment Definition, as there can be operations in other steps that trigger actions on the experiment.

Info


It is possible to mark the Experiment Definition Step to ignore the any Sampling Plans so that it does not affect the normal production sampling strategy.

Info

It is possible to mark the Experiment Definition Step to ignore the any SPC Charts so that it does not affect the normal production SPC strategy.

Material Groups

In the case of an Experiment with Sub-Materials, you need to specify the Sub-Materials Groups. It is possible to use the predefined Experiment Definition Groups, or to specify new ones, as shown in the image below. A matrix view is also available by selecting the respective icon on the top right-hand corner of the screen.



For each step's material group, you need to define the **Split Type**, i.e. the way the material will be split across the experiment, which can be: **None**, **Physical** or **Logical**, as shown in the image below. For the **Split Type** option **None**, no further configuration needs to be performed. For the **Split Type** Physical or Logical, you need to define the **Split Scope**, and when applicable the **Merge Flow Path**.

Info

The **Split Type** is only defined if the selected Experiment Definition Mode is Sub-Materials.

+ Add Experiment Definition Step

① GENERAL DATA — ② ACTION GROUPS — ③ ACTIONS

Step Action Groups

1 | 2 | 3 | 4

6 | 9

+ 🗑️ Action Group Details

* Sub-Materials:

Process 1 × ▾

* Ignore in Sampling Plans:

☐

* Ignore in SPC Charts:

☒

* Split Type:

Physical × ▾

Split Scope:

For Multiple Steps × ▾

Merge Flow Path:

CookiesFlow

☒ Moulding × 🔍

Browse

Flow Path:

CookiesFlow [B] > Moulding

Merge State:

Queued × ▾

Empty Sub-Materials: 5 | 8

CookiesFlow > Packing

Comments:

Cancel

< Back

Next >

Actions

In the Actions tab, you can define which actions will be performed for each Material Group, as shown in the image below. Each action must define the event when the action will be triggered: **Queued**, **Track-In**, **Track-Out** or **Processed**. The available events depend on the selected action, as can be checked in the table below.

+ Add Experiment Definition Step

Step Material Group Actions

MATERIAL GROUPS	
1 2 3 4 1 Action	ChangeFlowAndStep Processed
6 9 No actions	

+ □ ↑ ↓

Action Details

Action: Change Flow And Step

* Event: Processed

Distribution List:

Comment:

Change Flow And Step Details

* Flow and Step:

Cooling

Browse

Flow Path: CookiesFlow [B] > Cooling

CookiesFlow > Packing

Comments:

Cancel


< Back













Add

It's not necessary to define actions for every Material Group as by default, all Material Groups will follow the standard process unless there is an explicit action defined.


The table below presents a list of possible combinations between **Actions** and **Events**:

Action	Requires Split	Queued / Track-In / Track-Out / Processed	Exit Step	Additional Information	
Terminate	Physical Split or Full Lot	 X X 		Must be the last action for the event. If set at Queued, no actions can be set at other events. It is not possible to have at the same Step and State - Create Send Ahead Run and Terminate.	ExperimentDefinition. ActionTerminate
Hold	Physical Split or Full Lot	 X X 		For the same event - must be the first action for the event or the second action if preceded by a Set Note, Send Mail, Split or Merge.	ExperimentDefinition. ActionHold
Change Flow And Step	Physical Split or Full Lot	 X X 		Must be the last action for the event. If set at Queued, no actions can be set at other events.	ExperimentDefinition. ActionChangeFlowAndStep
Skip Step	Physical Split or Full Lot	 X X X		Must be the only action for the Experiment Definition Step Material Group.	ExperimentDefinition. ActionSkipStep

Action	Requires Split	Queued / Track-In / Track-Out / Processed	Exit Step	Additional Information	
Temporary Off Flow	Physical Split or Full Lot	✓ × × ✓	✓	Must be the last action for the event. If set at Queued, no actions can be set at other events.	ExperimentDefinition. ActionTemporaryOffFlow
Create Send-Ahead Run	Physical Split or Full Lot	✓ × × ×	⊖	It is not possible to have at the same Step and State - Create Send Ahead Run and Terminate. For the same event - must be the first action or must be preceded by a Send Mail, Send Note, Split or Merge.	ExperimentDefinition. ActionCreateSendAheadRun
Set Measure All	No	× ✓ × ×	⊖		ExperimentDefinition. ActionSetMeasureAll
Set BOM	Physical or Logical, if not Full Lot	× ✓ × ×	⊖		ExperimentDefinition. ActionSetBOM
Set Durables	Physical or Logical, if not Full Lot	× ✓ × ×	⊖		ExperimentDefinition. ActionSetDurables
Set Checklist	Physical or Logical, if not Full Lot	× ✓ ✓ ✓	⊖	Long Running Checklists are only possible for the Track-In event.	ExperimentDefinition. ActionSetChecklist

Action	Requires Split	Queued / Track-In / Track-Out / Processed	Exit Step	Additional Information	
Set Data Collection	Physical or Logical, if not Full Lot	×    		Long Running and Long Running after Track-In is only possible for the Track-In event.	ExperimentDefinition. ActionSetDataCollection
Set Recipe	Physical or Logical, if not Full Lot	×  × ×			ExperimentDefinition. ActionSetRecipe
Set Note	Physical or Logical, if not Full Lot	 ×  ×		For the same event - must be the first action for the event or the second action if preceded by a Send Mail, Split or Merge.	ExperimentDefinition. ActionSetNote
Set Resource	Physical or Logical, if not Full Lot	 × × ×		If defined, there must be no actions for the state Queued of the following type: - Terminate - Change Flow And Step - Skip Step - Temporary Off-Flow	ExperimentDefinition. ActionSetResource

Action	Requires Split	Queued / Track-In / Track-Out / Processed	Exit Step	Additional Information	
Set Service	Physical or Logical, if not Full Lot	 X X X		If defined, there must be no actions for the state Queued of the following type: - Terminate - Change Flow And Step - Skip Step - Temporary Off-Flow	ExperimentDefinition. ActionSetService
Send Mail	Physical or Logical, if not Full Lot	 X X 		For the same event - must be the first action for the event or the second action if preceded by a Set Note, Split or Merge.	ExperimentDefinition. ActionSendMail

Action	Requires Split	Queued / Track-In / Track-Out / Processed	Exit Step	Additional Information	
Split	Physical or Logical, if not Full Lot	   		<p>If set at Queued, the event must:</p> <ul style="list-style-type: none"> - be the first action for the Split To Material Group. - be the only action for the Split From Material Group at the Step. <p>If any other action is required, you can specify the split as part of the action.</p> <p>If set at Processed:</p> <ul style="list-style-type: none"> - the Split To Material Groups must not have other actions defined for the Queued state. <p>The same Material Group can only be part of one action of type Split or Merge for the same state.</p>	ExperimentDefinition. ActionSplit










Action	Requires Split	Queued / Track-In / Track-Out / Processed	Exit Step	Additional Information	
Merge	Physical or Logical, if not Full Lot	   		If set, the event must be the first action for both the Merge To and Merge From Material Groups. No other actions for the Merged From Material Groups are possible at the same state (as the Material will be Terminated). The same Material Group can only be part of one action of type Split or Merge for the same state.	ExperimentDefinition. ActionMerge

Table: Experiment Management Actions restrictions


The icons in the table can be read as follows:

-  - possible
-  - not possible
-  - not available

Depending on the action, additional information may need to be provided, as shown in the table below.

Action	Action Details	Required Information
Terminate	It terminates the Material or Material Group.	- The Loss Reason for the Action Step

Action	Action Details	Required Information
Hold	It puts the Material or Material Group on hold.	<ul style="list-style-type: none"> - The Hold Reason for the Action's Step - The Release Code (optional) - The Release Role (optional)
Change Flow And Step	It changes the Material or Material Group to a different Flow and/or Step.	<ul style="list-style-type: none"> - The Flow Path to where the material will be sent. In order to avoid circular executions, it is not possible to send the material to a previous point in the flow.
Create Send-Ahead Run	Creates a Send-Ahead Run at the defined Step.	<ul style="list-style-type: none"> - Specific definitions to allow the creation of a Send-Ahead Run, including the Sub-Materials to add as send-ahead Materials, the Send-Ahead Split Type that will be performed to the Material that will be kept in the Waiting state, the Selection Mode and the Steps and Flows to configure the Send-Ahead Run, as well as the Results Capture Mode.
Skip Step	Skips the current Step.	<ul style="list-style-type: none"> - No required information
Temporary Off Flow	It sends the Material or Material Group to a different Flow and/or Step temporarily.	<ul style="list-style-type: none"> - The Off-Flow Reason for the Action's Step - The Go-To Flow Path
Set Measure All	Marks all the Materials in the Material Group to be measured (when <i>In-Step Sampling</i> is used for the Step).	<ul style="list-style-type: none"> - No required information
Set BOM	Overrides the BOM to be used for the Material or Material Group.	<ul style="list-style-type: none"> - The BOM of scope <i>Materials</i> - The Assembly Type - The Track-In Check Mode (for Assembly Type <i>AutomaticAtTrackOut</i>) - The Track-Out Losses Mode (for Assembly Type <i>AutomaticAtTrackOut</i>) - The Weigh And Dispense Mode (for Assembly Type <i>WeighAndDispense</i>)
Set Durables	Overrides the Durables BOM to be used for the Material or Material Group.	<ul style="list-style-type: none"> - The BOM of scope <i>Durables</i>
Set Checklist	Overrides the Checklist to be used for the Material or Material Group.	<ul style="list-style-type: none"> - The Checklist of scope <i>MaterialTracking</i> that can only be <i>LongRunning</i> if the event is Track-In
Set Data Collection	Overrides the Data Collection to be used for the Material or Material Group.	<ul style="list-style-type: none"> - The Data Collection - The Data Collection Type that can only be <i>LongRunning</i> or <i>LongRunningAfterTrackIn</i> if the event is Track-In - The Data Collection Limit Set (optional)

Action	Action Details	Required Information
Set Recipe	Overrides the Recipe or one or more parameters values of the recipe to be used for the Material or Material Group.	<ul style="list-style-type: none"> - The Recipe - The Recipe parameter value if Overridable
Set Note	Sets the <i>Note</i> to be displayed to the User for the Material or Material Group.	<ul style="list-style-type: none"> - The note (rich text) to be displayed
Set Resource	Sets the <i>Resource</i> to be used to process the Material.	<ul style="list-style-type: none"> - The Resource (of processing type Line or Process) that is TopMost and is Active, Non-Template and which provides any of the Step required Services. If the selected Resource is of DispatchScheduling type Dispatch, user can select to AutomaticDispatch to that Resource (defaults to false)
Set Service	Sets the <i>Service</i> to be used to process the Material in that Step.	<ul style="list-style-type: none"> - The Service must be of processing type Process (that is Active and Non-Template)
Send Mail	Sends an email notification.	<ul style="list-style-type: none"> - Distribution List field is mandatory. If Alarm Management is licensed, you must enable or not the Create Notification and complete the mandatory fields accordingly.
Merge	Specifies the way the Material will be merged across the Experiment Definition.	<ul style="list-style-type: none"> - Select the Material Groups or Materials to perform the merge action. Split Type is always none for this action - Within the Action tab define the Material Group or Material that will be merged and the Material Group(s) or Material(s) where the previous Material will be merged into  <ul style="list-style-type: none"> - See Experiment Management Actions restrictions table


Action	Action Details	Required Information
Split	Specifies the way the Material will be split across the Experiment Definition.	<p>- Select the Material Groups or Materials to perform the Split action. Split Type is always none for this action</p> <p>- Within the Action tab define the Material Group or Material that will be mSPlit and the Material Group(s) or Material(s) from where the previous Material will be Split into</p>  <p>- See Experiment Management Actions restrictions table</p>

Table: Action details

Warning

If Feature Level Security is enabled, then the Actions defined above are protected by a security feature. That protection means that if you don't have explicit access to the feature, you will not be able to use that Action in an **Experiment**.

Note

There is the special security feature ExperimentDefinition.**AllActions** that provides access to all the available Actions. You can read more about Feature Level Security on the [Security](#) page of the User Guide.

Using Experiment Management

Create Experiment

To validate the hypothesis of an Experiment Definition, the association with a Material needs to be performed. There are two ways to create an Experiment:

1. Select an Experiment Definition and then a Material.
2. Select a Material and then an Experiment Definition.

A Material to be selected for an Experiment definition must have the defined:

- Product or Product Group
- Flow
- Material Type
- Material Form (If defined in the Experiment Definition)
- The sub-material form and number of required sub-materials, if the selected Mode is Sub-Materials

After the selection of a Material and an Experiment Definition, if the Mode is Sub-Materials, you need to defined the sub-materials to be assigned to each Sub-Material Numbers of the Experiment Definition, as

shown on the image below. The system allows an automatic assignment of the sub-materials to each Sub-Material Numbers, as shown in the image below, with the options:

- **Sorted by Sub-Material Name** - the first experiment number is assigned with the first sub-material, sorted by name, with an ascending order.
- **Sorted by Container and Position** - the first experiment number is assigned with the first sub-material, sorted by Container, Position, with an ascending order.
- **Random** - positions are randomly assigned.

If the Maximum Number of Materials is defined, then the number of experiments records must not exceed this number.

Info

A Material can only be assigned to a single Experiment at one time.

Create Experiment

MATERIAL

SUB-MATERIALS

Experiment A.1

Assign Sub-Materials To Sub-Material Numbers

NUMBER AND MATERIAL GROUPS	SUB-MATERIAL AND CONTAINER
1 Process 1	Material20191100003
2 Process 2	Material20191100004

Sub-Material

Sub-Material: Material20191100004

State: Queued

Product: Belgas

Step: Mixing

Primary Quantity: 5 Kg

Type: Production

Facility: Cookie Factory

Flow: CookiesFlow

Comments:

Cancel

< Back

Create

Create Experiment

MATERIAL

SUB-MATERIALS

Experiment A.2

Assign Sub-Materials To Sub-Material Numbers

NUMBER AND MATERIAL GROUPS	SUB-MATERIAL AND CONTAINER
1 Process A	No Sub-Material
2 Process B	No Sub-Material

Sub-Material

Assign by Sub-Material Name

Assign by Container and Position

Assign Remaining Randomly

Clear

Comments:

Cancel


< Back

Create

Close Experiment

When the Material/Sub-materials reach the last Step of the Experiment and all the Actions have been performed, the Experiment transits to the Completed state.

If the Experiment has the **Close Experiment Automatically** set to `true`, then it will be Closed automatically, having the option to be edited before being closed. Otherwise, the Close button will be enabled on the Experiment page. Optionally, a Result and a Conclusion can be associated with the Experiment, as shown in the image below:



Close Experiment

Experiment A-000000001 (Completed)

Execution

Result: Success

Conclusions:

Failure

Inconclusive


Comments:

Cancel Close

Experiment Page

The Experiment page allows you to check its details, actions to be performed and associated sub-materials, for the Experiment Definition Mode of sub-materials. There are two available views: Details and Matrix.

In the Details view you see the configurations of the Experiment, the associated Material and Sub-materials, as shown in the image below:



Experiment LOT AC-031 (In Progress)

EXPERIMENT

General data

Name: Experiment LOT AC-031

Description: AC lots internal improvements

System State: In Progress

Universal State: Effective

Experiment definition: Experiment LOT AC-031

Information

Material: LOT-WFR.1090

Start Date:

End Date:

First Step: Tape Application

Last Step:

SUB-MATERIALS

NUMBER	MATERIAL	CONTAINER	MATERIAL GROUPS
1	Material-0123	CNT-A1 (1)	EXP Process
2	Material-0125	CNT-A1 (3)	EXP Process
3	Material-0200	CNT-A1 (5)	AI & Polyimide
4	Material-0220	CNT-A1 (6)	AI & Polyimide
5	Material-0300	CNT-B30 (8)	EXP Process
6	Material-0250	CNT-A1 (7)	EXP Process
7	Material-0330	CNT-B30 (16)	Poly etch process
8	Material-0225	CNT-A1 (12)	New design REV

A Matrix view is also available, and it displays the defined actions for each sub-material per Step and Material Group, as shown in the image below. By selecting a sub-material and expanding the lateral Details tab, further information can be consulted, related to the Experiment, Step, Action and Sub-material.

Refresh

Edit

Clone

Close

Terminate

Views

Experiment LOT AC-031 (Effective)

STEP: ALL

MATERIAL GROUP: ALL

ACTION: ALL

DETAILS

EXPERIMENT

Name:

Experiment LOT AC-031

Description:

AC lots internal improvements

System State:

In Progress

Universal State:

Effective

Experiment definition:

Experiment LOT AC-031

Material:

LOT-WFR.1090

Start Date:

01-May-2018

First Step:

Tape Application

STEP

Select a sub-material

Steps and Actions	EXP Process						Al & Polyimide						Spacer tuning with...						Poly etch process					
	1	2	5	6	14	22	3	4	10	11	12	13	15	16	17	18	19	7	20	21	23	24		
WaferStore Controller																								
Temporary Off Flow (At Track-in)	1	2	5	6	14			4		11	12	13	15											
Hold (At Track-in)	1	2	5	6	14			4		11	12	13												
Change Flow And Step (At Track-out)																					23	24		
Set BOM (Move next)																			0	21				
Hold (Move next)																			0	21				
Grinding																								
Set Checklist (At Track-in)	1	2	5	6	14	22																		
Set Checklist (At Track-in)													13						0	21				
Hold (At Track-out)													13						0	21				
Set Recipe (At Track-out)																					23	24		
Hold (At Track-out)																					23	24		
Tape Application																								

Material:

Material-1050

Product:

PDTR-02564

Step:

Wafer incoming

Primary quantity:

30 kg

Type:

Production

Facility:

WFR-facility

Flow:

Flow Controller

Container:

Container-01 (3)



Legal Information

Disclaimer

The information contained in this document represents the current view of Critical Manufacturing on the issues discussed as of the date of publication. Because Critical Manufacturing must respond to changing market conditions, it should not be interpreted to be a commitment on the part of Critical Manufacturing, and Critical Manufacturing cannot guarantee the accuracy of any information presented after the date of publication. This document is for informational purposes only.

Critical Manufacturing makes no warranties, express, implied or statutory, as to the information herein contained.

Confidentiality Notice

All materials and information included herein are being provided by Critical Manufacturing to its Customer solely for Customer internal use for its business purposes. Critical Manufacturing retains all rights, titles, interests in and copyrights to the materials and information herein. The materials and information contained herein constitute confidential information of Critical Manufacturing and the Customer must not disclose or transfer by any means any of these materials or information, whether total or partial, to any third party without the prior explicit consent by Critical Manufacturing.

Copyright Information

All title and copyrights in and to the Software (including but not limited to any source code, binaries, designs, specifications, models, documents, layouts, images, photographs, animations, video, audio, music, text incorporated into the Software), the accompanying printed materials, and any copies of the Software, and any trademarks or service marks of Critical Manufacturing are owned by Critical Manufacturing unless explicitly stated otherwise. All title and intellectual property rights in and to the content that may be accessed through use of the Software is the property of the respective content owner and is protected by applicable copyright or other intellectual property laws and treaties.

Trademark Information

Critical Manufacturing is a registered trademark of Critical Manufacturing.

All other trademarks are property of their respective owners.